


PixelFormStyle1 : TPixelFormStyle	
BackGround	bgTile
BorderShape	(TBorderShape)
ColorFrom	■ clNavy
ColorTo	□ clWhite
GradientType	gtVertical
Height	768
Name	PixelFormStyle1
Picture	(TBitmap)
Rescale	<input checked="" type="checkbox"/> True
ShowBackGroun	<input checked="" type="checkbox"/> True
Steps	0
>> SwipeCardType	stNone
SwipeList	(TSwipeList)
Tag	0
WaveList	
WaveOnShowInc	0
Width	1024


**Note:** This functionality requires POS v12.3.22.x or higher.

### Barcode Scan Support on Kiosk Stations

When a station is set up to function as a customer-facing kiosk, a new form style is required to enable the scanning of product barcodes. Note that scanning will not function on the Welcome or Out of Service screens.


For each kiosk form that will NOT be used to scan product barcodes:


1. Open the relevant kiosk form in Form Designer.
2. On the right side of the Form Designer, select TPixelFormStyle from the drop down at the top of the list of attributes.
3. Set the property SwipeCardType to stNone.
4. Click the  button beside SwipeList (TSwipeList). A dialog box appears.



5. Uncheck all boxes in the Swipe Types List.
6. Click OK and save the form.
7. Repeat these steps on any kiosk form that is NOT used for product selection.

On each kiosk form that will be used to scan product barcodes:

1. Open the relevant kiosk form in Form Designer.
2. On the right side of the Form Designer, select TPixelFormStyle from the drop down at the top of the list of attributes.
3. Set the property SwipeCardType to stBarCode.
4. Click the  button beside SwipeList (TSwipeList). A dialog box appears.
5. Check the box slBarCode.

A screenshot of a Windows-style dialog box titled "Swipe Types List". The dialog has a blue title bar. Inside, there's a section titled "Select and Sort Swipe Types" which contains a list of four items: "slBarCode" (checked), "slCouponBarCode", "slCreditCard", and "slMember". Below the list are "Up" and "Down" buttons. At the bottom of the dialog are "Help", "Ok", and "Cancel" buttons. The "Cancel" button is highlighted with a dashed border.

6. Click OK and save the form.
7. Repeat these steps for any other forms used for product selection that require product barcode scanning to be enabled.

**Note:** Scan functions can be enabled on any form by checking the appropriate box in the Swipe Types List. This includes Coupons and Members.

When information is scanned, the POS will check for a match with any of the swipe types that are checked in the Swipe Types List. If one box is checked, only one swipe type will be searched. If multiple boxes are checked, the search will run in the order the swipe types are displayed, from top to bottom, for checked boxes only. Swipe types can be reordered in this list using the Up and Down buttons.